

2025년 상반기 K-디지털 트레이닝


MongoDB 개요

[KB] IT's Your Life





MongoDB 다운로드

https://www.mongodb.com/




MongoDB 다운로드







MongoDB 설치


o mongodb-windows-x86_64-7.0.8-signed.msi 실행







mongodb-windows-x86_64-7.0.8-signed.msi 실행











MongoDB Shell 설치



MongoDB Shell 설치

- mongosh-2.2.2-win32-x64.zip
 - bin 폴더의 내용을 C:\Program Files\MongoDB\Server\7.0\bin에 복사
- o PATH 환경변수 수정
 - C:₩Program Files₩MongoDB₩Server₩7.0₩bin을 추가



💟 몽고 shell 실행 확인

> mongosh

Please enter a MongoDB connection string (Default: mongodb://localhost/):

Current Mongosh Log ID: 660df366b9d4eae6259f9909

Connecting to:

mongodb://127.0.0.1:27017/?directConnection=true&serverSelectionTimeoutMS=2000&appName=mon

gosh+2.2.2

Using MongoDB: 7.0.8 Using Mongosh: 2.2.2

For mongosh info see: https://docs.mongodb.com/mongodb-shell/

To help improve our products, anonymous usage data is collected and sent to MongoDB periodically (https://www.mongodb.com/legal/privacy-policy).

You can opt-out by running the disable Telemetry() command.


The server generated these startup warnings when booting

2024-04-04T09:16:00.291+09:00: Access control is not enabled for the database. Read and write access to data and configuration is unrestricted


test>


```
test> use my_database
switched to db my_database
my_database> db.users.insert({name: "Kyle"})
DeprecationWarning: Collection.insert() is deprecated. Use insertOne, insertMany, or bulkWrite.
 acknowledged: true,
 insertedIds: { '0': ObjectId('660df5956bc6400e4f9f990a') }
my_database> db.users.find()
[ { _id: ObjectId('660df5956bc6400e4f9f990a'), name: 'Kyle' } ]
```


MongoDBCompass





MongoDBCompass
















Studio 3T

o https://studio3t.com/



Studio 3T





Studio 3T

- o studio-3t-x64.zip의 studio-3t-x64.exe 실행
 - 디폴트로 설치


ㅇ 첫 실행


- 계정 로그인 필요
 - 필요한 경우 회원 가입







⊀ KB 국민은행









★ KB국민은항

